



Yealink Meeting Server Streaming Guide

Version 20.0.0.5
Dec.2018

About This Guide

This guide introduces how to use RTMP protocol to stream a conference to You Tube, therefore the users on You Tube can watch the live broadcast of the conference.

In This Guide

Topics in this guide include:

- Chapter 1 [Obtaining the RTMP Address](#)
- Chapter 2 [Inviting You Tube from the Conference Control](#)

Table of Contents

About This Guide	iii
In This Guide.....	iii
Table of Contents	v
Obtaining the RTMP Address.....	1
Creating a Creator Studio	2
Inviting You Tube from the Conference Control	5

Obtaining the RTMP Address


Before streaming the conference to YouTube, you need obtain the RTMP address.

Before you begin


You have created a Creator Studio. If you do not have, refer to [Creating a Creator Studio](#) to create one.

Procedure

1. Click **SIGN IN** to log into YouTube.




2. Click **Creator Studio**.



3. Click **Live Streaming**->**Stream now**.
4. Go to **ENCODER SETUP** (in the bottom of the page), and copy the Server URL and the Stream name/key to generate the RTMP address.

The RTMP address: "Server URL" + "/" + "Stream name/key".

(Optional) After you succeed in streaming the conference, you can go to the bottom of the Creator Studio to share the live broadcast with others.



Creating a Creator Studio


If you have a You Tube account but not a Creator Studio, you need create one first.

Procedure


1. Log into You Tube.

2. Click **You Tube Studio (Beta)**, and create your own channel according to the prompts.


If it succeeds, the page is displayed like the follow:



3. Click **YOU TUBE STUDIO (BETA)** to go to the You Tube Studio (Beta) page.
4. Click **Settings->Creator Studio Classic->SAVE.**



5. Click **Live Streaming**->**Stream now**->**Get started**.



6. Complete the account verification according to the prompts to generate your Creator Studio.

Inviting You Tube from the Conference Control

You can enter the RTMP address on the Invite page to invite the users in You Tube to watch the live broadcast of the conference.

Procedure

1. Schedule a video conference, and go the Conference Control page as a moderator.
2. Click **Invite** in the top-right corner.
3. Select **Invite Others**.
4. Select **RTMP** from the drop-down menu, enter the RTMP address to streaming the conference to You Tube.
(Optional.) Select the Dual Stream checkbox, to share the video and the content separately with the users.

Invite Participants

[Invite Contacts](#) [Invite Others](#) [Email Invitation](#)

Call H.323/SIP device, SfB(Lync) client or RTMP addresses


Protocol :

RTMP address :

Dual Stream

5. Click **Call**.

If the streaming succeeds, the page is shown as below:



6. Go back to You Tube, and you can watch the live broadcast.

Customer Feedback

We are striving to improve our documentation quality and we appreciate your feedback. Email your opinions and comments to DocsFeedback@yealink.com.

Technical Support

Visit Yealink WIKI (<http://support.yealink.com/>) for the latest firmware, guides, FAQ, Product documents, and more. For better service, we sincerely recommend you to use Yealink Ticketing system (<https://ticket.yealink.com>) to submit all your technical issues.